



Pregnancy Testing

Pregnancy test results recorded in **koolcollect** can be submitted to BREEDPLAN for analysis using the **koolperform** BREEDPLAN Export Wizard.

BREED PLAN EXPORT full screen close

BREEDPLAN EXPORT

Welcome to the BREEDPLAN Export Wizard.

This wizard will take you through the process of selecting your animals for submission, validating and sending the data to BREEDPLAN.

Please click 'next' to begin and follow the steps on each page.

next

Missing Data? Re-Run Setup Wizard Sapien Technology

Go to **koolperform** > Data Move > BREEDPLAN Export

BREED PLAN EXPORT full screen close

Choose your export type.

- Registration
- Weights and Scans and Traits
- Joining
- Preg Testing
- Fates
- Trait Observation
- Structural Score

Select this option export type to export your Preg Testing Results.

STEP 1 OF 6

next

Missing Data? Re-Run Setup Wizard Sapien Technology

Step 1 – Choose the export type you require > Preg Testing



Pregnancy Testing

BREED PLAN EXPORT - PREG TESTING EXPORT full screen close

We need to know how you want to select your animals...

Animals in current list : 'Breedplan Pregtesting'

Another Worklist

Session

Created	Description	Modified	Head
cattle	BPExport_Temp	17/03/2015	76
cattle	Breedplan Fates	06/11/2012	12
cattle	Breedplan Fates - Inactive	12/02/2015	8
cattle	Breedplan Joins	02/12/2011	109
cattle	Breedplan Pregtesting	02/12/2011	100
cattle	Breedplan Registration export	01/12/2011	88
cattle	Breedplan Structure Score	01/12/2011	41
cattle	Breedplan Weights Traits	02/12/2011	77
cattle	cattle Temporary	17/03/2015	76
cattle	Copy Of Breedplan Registration ex...	30/09/2014	88
cattle	Copy Of cattle Temporary	17/03/2015	6
cattle	D1 2007 Active cattle	27/09/2011	77

STEP 2 OF 6 back next

Missing Data? Re-Run Setup Wizard Sapien Technology

Step 2 – Select the animals you wish to submit. You can do this using the preg testing session created in **koolcollect** or by creating a worklist in the Animals tab of **koolperform**.

BREED PLAN EXPORT - PREG TESTING EXPORT full screen close

We have some additional questions.

from to Select the date range that the pregnancy tests were taken.

session type Only select a session type to eliminate statuses recorded in other sessions.

STEP 3 OF 6 back next

Missing Data? Re-Run Setup Wizard Sapien Technology

Step 3 – Complete preg testing session dates and type.



Pregnancy Testing

BREED PLAN EXPORT - PREG TESTING EXPORT full screen close

Review your data.
records found: 47

	society id	preg test date	preg test result
▶	SAPSCPA022	20110427	12
	SAPSCPA023	20110427	12
	SAPSCPA025	20110427	14
	SAPSCPA026	20110427	14
	SAPSCPA027	20110427	10
	SAPSCPA028	20110427	12
	SAPSCPA029	20110427	10
	SAPSCPA030	20110427	12
	SAPSCPA031	20110427	12
	SAPSCPA032	20110427	12
	SAPSCPA033	20110427	12
	SAPSCPA034	20110427	14
	SAPSCPA035	20110427	12
	SAPSCPA036	20110427	12

STEP 4 OF 6 back next

[Missing Data? Re-Run Setup Wizard](#) Sapien Technology

Step 4 – Review the data, which should display P (pregnant), N (not pregnant) or 3-20 (weeks pregnant).

BREED PLAN EXPORT - PREG TESTING EXPORT full screen close

Review any validation errors or warnings.

There are errors in the data that MUST be fixed before proceeding to the next screen.

Row 1 - [] *****ERROR***** A Society Id has not been recorded.

STEP 5 OF 6 back next

[Missing Data? Re-Run Setup Wizard](#) Sapien Technology

Step 5 – Submission data is validated. The submission cannot proceed if any animals create an *****ERROR***** message. Warnings should also be reviewed and fixed where possible, but will not stop the submission.



Pregnancy Testing

BREED PLAN EXPORT - PREG TESTING EXPORT full screen close

Review any validation errors or warnings.

There were no validation issues. Press 'next' to continue.

STEP 5 OF 6 back next

Missing Data? Re-Run Setup Wizard Sapien Technology

BREED PLAN EXPORT - PREG TESTING EXPORT full screen close

Save the results to file to send to BREEDPLAN.
Enter the file name and click on the save button.

export filename

export folder
 save

STEP 6 OF 6 back finish

Missing Data? Re-Run Setup Wizard Sapien Technology

Step 6 – Save the export in your preferred file location. You will then be prompted to email the file directly to BREEDPLAN.